

API GETSYSTEMMETRICS

declaration

Declare Function GetSystemMetrics Lib "user32" (ByVal nIndex As Long) As Long

Constante	Valeur	Définition
SM_CXSCREEN	0	Return the width of the screen.
SM_CYSCREEN	1	Return the height of the screen.
SM_CXVSCROLL	2	Win 95/98 only: Return the width of a vertical scrollbar.
SM_CXHSCROLL	3	Win 95/98 only: Return the height of a horizontal scrollbar.
SM_CYCAPTION	4	Return the height of a normal caption area.
SM_CXBORDER	5	Win NT: Return the width of a window border. Win 95/98: Return the width of a single window border.
SM_CYBORDER	6	Win NT: Return the height of a window border. Win 95/98: Return the height of a single window border.
SM_CXDLGFRAME	7	Win NT only: Return the width of a window frame having a dialog frame style.
SM_CYDLGFRAME	8	Win NT only: Return the height of a window frame having a dialog frame style.
SM_CVTHUMB	9	Return the height of a vertical scrollbar thumb.
SM_CXTHUMB	10	Return the width of the horizontal scrollbar thumb.
SM_CXICON	11	Return the default width of an icon.
SM_CYICON	12	Return the default height of an icon.
SM_CXCURSOR	13	Win NT: Return the width of the cursor. Win 95/98: Return the width of the standard cursor bitmap.
SM_CYCURSOR	14	Win NT: Return the height of the cursor. Win 95/98: Return the height of the standard cursor bitmap.
SM_CYMENU	15	Return the height of a single menu bar.
SM_CXFULLSCREEN	16	Return the width of the client area of a full-screen window.
SM_CYFULLSCREEN	17	Return the height of the client area of a full-screen window.
SM_CYKANJIWINDOW	18	Return the height of the Kanji window (for double-byte character set versions of Windows).
SM_MOUSEPRESENT	19	Return a non-zero value if a mouse is installed and present, 0 if not.
SM_CYVSCROLL	20	Win 95/98 only: Return the height of an arrow bitmap on a vertical scrollbar.
SM_CXHSCROLL	21	Win 95/98 only: Return the width of an arrow bitmap on a horizontal scrollbar.
SM_DEBUG	22	Return a non-zero value if the debugging version of USER.EXE is installed, 0 if not.
SM_SWAPBUTTON	23	Return a non-zero value if the left and right mouse buttons are swapped, 0 if not.
SM_CXMIN	28	Return the minimum width of a window.
SM_CYMIN	29	
SM_CXSIZE	30	Win NT: Return the width of a title bar bitmap. Win 95/98: Return the width of a caption button.
SM_CYSIZE	31	Win NT: Return the height of a title bar bitmap. Win 95/98: Return the height of a caption button.
SM_CXFRAME	32	Win NT only: Return the width of the border of a resizable window.
SM_CXSIZEFRAME	32	Win 95/98 only: Return the width of a thick window frame.
SM_CYFRAME	33	Win NT only: Return the height of the border of a resizable window.
SM_CYSIZEFRAME	33	Win 95/98 only: Return the height of a thick window frame.
SM_CXMINTRACK	34	Win 95/98 only: Return the default minimum width the user is allowed to resize a window to.
SM_CYMINTRACK	35	Win 95/98 only: Return the default minimum height the user is allowed to resize a window to.
SM_CXDOUBLECLK	36	The width of the rectangle within which both mouse clicks must be to recognize a double-click.
SM_CYDOUBLECLK	37	Return the height of the rectangle within which both mouse clicks must be to recognize a double-click.
SM_CXICONSPACING	38	Win NT: Return the width of the cell used to position icons. Win 95/98: Return the width of the grid cell for items in a large icon view.
SM_CYICONSPACING	39	Win NT: Return the height of the cell used to position icons. Win 95/98: Return the height of the grid cell for items in a large icon view.
SM_MENUDROPALIGNMENT	40	Return a non-zero value if popup menus appear to the right, 0 if to the left.
SM_PENWINDOWS	41	Return a non-zero value if the Microsoft Windows for Pen computing extensions are installed, 0 if not.
SM_DBCSENABLED	42	Return a non-zero value if the double-byte character set version of USER.EXE is installed, 0 if not.
SM_MOUSEBUTTONS	43	Return the number of mouse buttons on the installed mouse, or 0 if no mouse is installed.
SM_CMETRICS	44	
SM_SECURE	44	Return a non-zero value if security is present and active, 0 if not.
SM_CXEDGE	45	Win 95/98 only: Return the width of a 3D window border.
SM_CYEDGE	46	Win 95/98 only: Return the height of a 3D window border.
SM_CXMINSPACING	47	Win 95/98 only: Return the width of the grid cell rectangle used to position minimized windows.
SM_CYMINSPACING	48	Win 95/98 only: Return the height of the grid cell rectangle used to position minimized windows.
SM_CXSMICON	49	Win 95/98 only: Return the recommended width for small icons.
SM_CYSMICON	50	Win 95/98 only: Return the recommended height for small icons.
SM_CYSMCAPTION	51	Win 95/98 only: Return the height of a small caption area.
SM_CXSMSIZE	52	Win 95/98 only: Return the width of a small caption button.
SM_CYSMSIZE	53	Win 95/98 only: Return the height of a small caption button.
SM_CXMENUSIZE	54	Win 95/98 only: Return the width of a menu bar button.
SM_CYMENUSIZE	55	Win 95/98 only: Return the height of a menu bar button.
SM_CXMINIMIZED	57	Win 95/98 only: Return the width of a normal minimized window.
SM_CYMINIMIZED	58	Win 95/98 only: Return the height of a normal minimized window.
SM_CXMAXTRACK	59	Win 95/98 only: Return the default maximum width the user is allowed to resize a window to.
SM_CYMAXTRACK	60	Win 95/98 only: Return the default maximum height the user is allowed to resize a window to.
SM_CXMAXIMIZED	61	Win 95/98 only: Return the default width of a maximized window.
SM_CYMAXIMIZED	62	Win 95/98 only: Return the default height of a maximized window.
SM_NETWORK	63	Set the &H1 bit of the return value if a network is installed. All other bits of the return value are reserved and undefined.
SM_CLEANBOOT	67	Win 95/98 only: Return a value specifying how the computer was booted up. 0 means a normal bootup, 1 means a fail-safe (a.k.a. SafeBoot) bootup, and 2 means a fail-safe bootup with the network installed.
SM_CXDRAG	68	Return the minimum width the cursor must move to begin a drag-and-drop operation.

SM_CYDRAG	69	Return the minimum height the cursor must move to begin a drag-and-drop operation.
SM_SHOWSOUNDS	70	Return a non-zero value if the application should show a visual cue for all sounds, 0 if not.
SM_CXMENUCHECK	71	Win 95/98 only: Return the width of the default menu check-mark bitmap.
SM_CYMENUCHECK	72	Win 95/98 only: Return the height of the default menu check-mark bitmap.
SM_SLOWMACHINE	73	Return a non-zero value if the system has a slow, low-end processor, 0 if not.
M_MIDEASTENABLED	74	Return a non-zero value if the system is enabled to use Hebrew and Arabic languages, 0 if not.